

AUTUMN IN NEW ENGLAND

38" x 50"



Designed & Pieced by:
Carolyn Burgess & Heidi Herzog Dietz

Quilted by:
Carolyn Burgess

Appliques Quilts and More

MATERIALS:

[1] ANESH Panel

1/2 yard Autumn Splendor

1/3 yard Blender Everglade

1/3 yard Blender Canary

1/3 yard Blender Paprika

1/3 yard Blender Cherry

1-1/2 yards Backing

1-1/3 yards of 45" wide or 1 yard 60" wide
Batting

BEFORE SEWING, READ ALL INSTRUCTIONS.
ALL SEAMS ARE 1/4" UNLESS OTHERWISE
STATED. CUTTING INSTRUCTIONS ARE BASED
ON 40" WOF. WOF = WIDTH OF FABRIC;
RST = RIGHT SIDES TOGETHER

CUTTING:

From Autumn Splendor Fabric:

Cut [5] — 3" × WOF strips

From each of the Blender Fabrics:

Cut [2] — 5" × WOF strips

Subcut [16] — 5" squares

Panel Assembly:


1. Trim the ANESH Panel to 1/4" from outer edge of white border. It should be as large as you can make it, approximately 29" × 43".
2. Take [1] of the Autumn Splendor 3" strips and stitch to the top of the Panel. Repeat with the bottom strip. Press seams and trim.
3. Cut [1] Autumn Splendor 3" strip in half and stitch to [1] end of each of the remaining strips.
4. Stitch [1] strip to right and left sides of the Panel. Press seams and trim.

Prairie Points:

1. Using the Blender Canary, Blender Everglade, Blender Paprika and Blender Cherry 5" squares, fold each wrong side together

diagonally to form a triangle. Fold the triangle along its longest edge, taking care to align the edges together. Pressing with steam helps keep the folds intact. Repeat with remaining squares.

2. With RST, evenly space the prairie points along the edges of quilt top, pinning as you go. Diagram below is not to scale.



3. Make certain all open ends of the prairie points are pointing left. Starting on the left side place a prairie point in the corner at 0 on the ruler. Put the next prairie point on top of the first one at 3 on the ruler, then 6, then 9 etc. Proceed with the remaining prairie points. A slight adjustment might be necessary at the corners. (You may have some prairie points left over). Baste the prairie points along the edges.

QUILT ASSEMBLY:

1. At [1] of the short ends, measure approximately 10" from each edge and mark. this is the opening needed to flip the quilt right side out.
2. Place the batting on the table. Place the backing fabric, right side facing up on top of the batting.
3. Next with RST, place the top section on the backing fabric with the prairie points inside and the raw edges facing out. The batting will be on the bottom at this point.
4. Begin stitching at the second 10" mark. Be sure to back stitch, as this will make the seam more secure when it comes time to flip the quilt right side out. Continue to stitch around the entire quilt until you reach the other 10" mark. You will be stitching over the same stitches that were used to secure the prairie points.



5. Press to set seams. Trim corners, if necessary, to remove bulk. Turn quilt right side out. Press the prairie points outward.
6. Fold the opening fabric in 1/4". Press. Whip stitch opening closed.

QUILTING:

1. Stitch in the ditch around the borders to secure the batting. Or, use your favorite quilting design or technique to finish.

Carolyn Burgess & Heidi Herzog Dietz



Carolyn and Heidi have been designing patterns and vending at quilt shows together since 2012. Their Mission is to provide you with quality unique products to help you create beautiful quilts, accurately and as easily as possible. They offer a variety of appliques, silhouettes, quilt kits, patterns, and more, along with custom laser cutting. They also host machine embroidery classes and monthly sit-and-sews with snacks!